

worker_lookup

Synopsis

`worker_lookup = precedence`

Specifies the *precedence* for this Worker's configuration look up. This allows an administrator to either disable all remote configuration, rely only on remote configuration or determine which overrides the other. By default the Supervisor's transmitted configuration overrides the local configuration.



Note for Qube Worker hosts

This is a Worker startup parameter. Since this parameter is involved in the initial startup of the worker and affects the behavior of the worker before it contacts the supervisor to request a "remote" configuration from the central worker configuration file (see [qbwrk.conf](#)), it's considered a *bootstrapping* parameter and *can only be specified in the worker's local qb.conf* configuration file. Any mention in the global qbwrk.conf file will be ignored.

This is a complete list of the Worker bootstrap parameters

- `qb_directory`
- `qb_domain`
- `qb_supervisor`
- `worker_address`
- `worker_boot_delay`
- `worker_journal_location`
- `worker_lookup`
- `worker_max_threads`
- `worker_pidfile`
- `worker_port`



In order to prevent the worker from requesting a remote configuration from the supervisor, set the `worker_lookup = local`

Examples

Use only local configuration:

```
worker_lookup = local
```

Use only remote configuration:

```
worker_lookup = supervisor
```

Local configuration overrides the Supervisor's config:

```
worker_lookup = supervisor,local
```

Supervisor's configuration overrides the local config:

```
worker_lookup = local,supervisor
```

Defaults

local,supervisor